



IxChariot API Guide

IxChariot 9.5, August 2017



Copyright and Disclaimer

Copyright © 2017 Ixia. All rights reserved.

This publication may not be copied, in whole or in part, without Ixia's consent.

Ixia, the Ixia logo, and all Ixia brand names and product names in this document are either trademarks or registered trademarks of Ixia in the United States and/or other countries. All other trademarks belong to their respective owners.

The information herein is furnished for informational use only, is subject to change by Ixia without notice, and should not be construed as a commitment by Ixia. Ixia assumes no responsibility or liability for any errors or inaccuracies contained in this publication.

RESTRICTED RIGHTS NOTICE

As prescribed by FAR 27.409(b)(4) and in accordance with FAR 52.227-14, please take notice of the following.

(a) This proprietary computer software and/or software technical data is submitted with restricted rights. It may not be used, reproduced, or disclosed by the Government except as provided in paragraph (b) of this notice or as otherwise expressly stated in the applicable contract.

(b) This computer software and/or software technical data may be—

(1) Used or copied for use with the computer(s) for which it was acquired, including use at any Government installation to which the computer(s) may be transferred;

(2) Used or copied for use with a backup computer if any computer for which it was acquired is inoperative;

(3) Reproduced for safekeeping (archives) or backup purposes;

(4) Modified, adapted, or combined with other computer software, provided that the modified, adapted, or combined portions of the derivative software incorporating any of the delivered, restricted computer software shall be subject to the same restricted rights;

(5) Disclosed to and reproduced for use by support service Contractors or their subcontractors in accordance with paragraphs (b)(1) through (4) of this notice; and

(6) Used or copied for use with a replacement computer.

(c) Notwithstanding the foregoing, if this computer software and/or software technical data is copyrighted computer software and/or software technical data, it is licensed to the Government with the minimum rights set forth in paragraph (b) of this notice.

(d) Any other rights or limitations regarding the use, duplication, or disclosure of this computer software and/or software technical data are to be expressly stated in, or incorporated in, the applicable contract.

(e) This notice shall be marked on any reproduction of this computer software, in whole or in part.

(End of notice)

Contacting Ixia

Corporate Headquarters	<p>Ixia Worldwide Headquarters 26601 W. Agoura Rd. Calabasas, CA 91302 USA +1 877 FOR IXIA (877 367 4942) +1 818 871 1800 (International) (FAX) +1 818 871 1805 sales@ixiacom.com</p>	<p>Web site: www.ixiacom.com General: info@ixiacom.com Investor Relations: ir@ixiacom.com Training: training@ixiacom.com Support: support@ixiacom.com +1 818 595 2599</p>
EMEA	<p>Ixia Europe Limited Part 2nd floor, Clarion House, Norreys Drive Maidenhead, UK SL6 4FL +44 (1628) 408750 FAX +44 (1628) 639916 salesemea@ixiacom.com</p>	<p>Support: support-emea@ixiacom.com +40 21 301 5699</p>
Asia Pacific	<p>Ixia Pte Ltd 210 Middle Road #08-01 IOI Plaza Singapore 188994</p>	<p>Support: support-asiapac@ixiacom.com +91 80 4939 6410</p>
Japan	<p>Ixia KK Nishi-Shinjuku Mitsui Bldg 11F 6-24-1, Nishi-Shinjuku, Shinjuku-ku Tokyo 160-0023 Japan</p>	<p>Support: support-japan@ixiacom.com +81 3 5326 1980</p>
India	<p>Ixia Technologies Pvt Ltd Tower 1, 7th Floor, UMIYA Business Bay Cessna Business Park Survey No. 10/1A, 10/2, 11 & 13/2 Outer Ring Road, Varthur Hobli Kadubeesanahalli Village Bangalore East Taluk Bangalore-560 037, Karnataka, India +91 80 42862600</p>	<p>Support: support-india@ixiacom.com +91 80 4939 6410</p>
China	<p>Ixia Technologies (Shanghai) Company Ltd Unit 3, 11th Floor, Raffles City, Beijing Beijing, 100007 P.R.C.</p>	<p>Support: support-china@ixiacom.com 400 898 0598 (Greater China Region) +86 10 5732 3932 (Hong Kong)</p>

This page intentionally left blank.

Contents

Contacting Ixia	3
IxChariot WebAPI Guide	7
Requirements	7
Installation	7
Sample Scripts	9
Accessing the API	29
Connection Methods	29
IxChariotApi Methods	31
Session Methods	49
Statistic Class	56
StatisticValue Class	56
WebObjects	57

[This page intentionally left blank]

IxChariot WebAPI Guide

The IxChariot WebAPI library is a collection of Python utilities that enable you to create Python scripts that can access the same capabilities as the IxChariot GUI.

Through the WebAPI library, you can create and manage sessions, load and save test configurations, and run tests. The library also provides helpers for accessing web app-specific URLs, and for creating and modifying the JSON (JavaScript Object Notation) data that IxChariot uses.

Requirements

To use the IxChariot WebAPI, you also need the following software:

- Python, the scripting language and development environment
- virtualenv, a tool for creating isolated ("sandboxed") Python environments, and pip, a tool for installing and managing Python packages (included with virtualenv)
- Requests, an HTTP library for Python
- the WebAPI

You can run the WebAPI scripts from the same PC where IxChariot is installed, or from a separate PC, as long as the separate PC can communicate with the IxChariot host.

Where you will run WebAPI scripts from	Install:
Same PC where IxChariot is installed	<ul style="list-style-type: none">• Python 2.7.9 or later version of 2.7 (Python 3 is not supported)• Requests 1.1.0 - 2.3.0 (Requests versions higher than 2.3.0 are not supported)• WebAPI
Different PC from where IxChariot is installed	<ul style="list-style-type: none">• Unix/Linux, OS X, or Windows (XP or later)• Python 2.7.9 or later version of 2.7 (Python 3 is not supported)• Requests 1.1.0 - 2.3.0 (Requests versions higher than 2.3.0 are not supported)• WebAPI

Installation

This section describes how to install the IxChariot WebAPI and its supporting software.

Installing Python

1. Download Python 2.7.9 or later version of 2.7 from the [Python website](#). WebAPI does not support Python 3.

2. Follow the instructions on the website to install Python.
3. After installation is complete, add the Python directory to the system PATH environment variable. The default directory is `C:\Python27`.

Installing the virtualenv and Requests

Windows

The following procedure describes one procedure for installing the [Requests](#) libraries. The Requests website describes other procedures.

1. Download [virtualenv](#). virtualenv comes with pip and all its prerequisites.
2. Extract the contents of the downloaded zip file to a temporary folder (for example `C:\temp\virtualenv`). You may also need to extract the tar file under the new directory.
3. Open a console window and change the path to the distribution folder (for example: `C:\temp\virtualenv`).
4. Run the virtualenv install script. Type:

```
python setup.py install
```
5. After the install script completes, create a Python sandbox. From the same directory, type:

```
python virtualenv.py c:\webapi
```

The sandbox allows you to install things without affecting your main Python installation or other instances of virtualenv .
6. Activate the sandboxed virtualenv (named `webapi` in this example). Type:

```
c:\webapi\scripts\activate
```

After activation, the command prompt displays `(webapi)` ahead of the path (for example: `(webapi) c:\temp>`). You will need to enter the `activate` command before running any WebAPI scripts. Once the virtualenv is active, pip is available to install almost any Python package, including Requests.
7. Install Requests. Type:

```
python -m pip install -Iv requests==2.3.0
```

After installation, Requests is available.

NOTE

WebAPI does not support a requests version higher than 2.3.0.

Linux

Linux installation should be possible through your release-specific package manager. If Requests is not directly available through the GUI, you should be able to select the pip module with your Python installation, and then use that to install requests (for example, `pip install requests==2.3.0`).

Otherwise, use the Windows installation procedure as a guide - you will need to perform similar steps, but you may also need to perform additional steps such as using the `sudo` command or logging in as root.

Installing the WebAPI

1. Download the WebAPI distribution file:
 - a. In the IxChariot GUI, go to **Help>Python API Library** and click the link.
The WebAPI .zip file is automatically downloaded.
 - b. Unzip the file to a folder of your choice.
2. Add the folder where you unzipped the .zip file to the PYTHONPATH environment variable. If you add the variable through the Windows GUI, you will need to launch a new command window so that the variable takes effect. If you are using virtualenv, you will need to activate it as described in [Installing the virtualenv and Requests](#).
3. To confirm that everything is installed correctly, start Python, and then from the Python command prompt, type:

```
import ixia.webapi
```

If the installation is correct, the command will succeed (no message appears).
You can proceed to running an IxChariot sample script.

Sample Scripts

Several sample scripts are included with the IxChariot WebAPI. You can use these scripts to familiarize yourself with the WebAPI, and as the basis for your own scripts.

IxChariot API Sample

To illustrate the general structure of an IxChariot API script, this section provides a commented sample script.

The script sample, `ixchariot_sample.py`, is available in the `\samples` subdirectory under the directory where the API archive was unzipped.

An [`ixchariotApi.py`](#) Python module is provided in the same subdirectory.

It is a wrapper over the WebAPI including the IxChariot specific functions and procedures, which must be used conjointly with the `ixchariot_sample.py` to get a general idea about the IxChariot WebAPI structure.

```
from ixia.webapi import *
import ixchariotApi

webServerAddress = "https://ixchariot-server"
apiVersion = "v1"
username = "N/A"
password = "N/A"
apiKey = "N/A"           # Get the API Key from the web interface, Menu > My Account > Api Key
```

```
print "Connecting to " + webServerAddress
api = webApi.connect(webServerAddress, apiVersion, None, username, password)
# It is also possible to connect with the API Key instead of username and password,
using:
#api = webApi.connect(webServerAddress, apiVersion, apiKey, None, None)

session = api.createSession("ixchariot")
print "Created session %s" % session.sessionId

print "Starting the session..."
session.startSession()

print "Configuring the test..."

# Configure few test options
testOptions = session.httpGet("config/ixchariot/testOptions")
testOptions.testDuration = 20
testOptions.consoleManagementQoS = ixchariotApi.getQoSTemplateFromResourcesLibrary
(session, "Best Effort")
testOptions.endpointManagementQoS = ixchariotApi.getQoSTemplateFromResourcesLibrary
(session, "Best Effort")
session.httpPut("config/ixchariot/testOptions", data = testOptions)

# Available endpoints used in test (list of 'testIP/mgmtIP' strings)
src_EndpointsList = ["192.168.1.100/192.168.1.101"]
dst_EndpointsList = ["192.168.1.200/192.168.1.201"]

# Create a new ApplicationMix
name = "AppMix 1"
objective = "USERS"
users = 20
direction = "SRC_TO_DEST"
topology = "FULL_MESH"
appmix = ixchariotApi.createApplicationMix(name, objective, users, direction, topo-
logy)
session.httpPost("config/ixchariot/appMixes", data = appmix)

# Configure endpoints for the AppMix

# This demonstrates how to manually assign endpoints to the test configuration using
known IP addresses.
# If you want to assign an endpoint discovered by the Registration Server, use the
ixchariotApi.getEndpointFromResourcesLibrary() function
# to get the data for httpPost
for src_Endpoint in src_EndpointsList:
```

```
        ips = src_Endpoint.split('/')
        session.httpPost("config/ixchariot/appMixes/1/network/sourceEndpoints", data =
ixchariotApi.createEndpoint(ips[0], ips[1]))
for dst_Endpoint in dst_EndpointsList:
    ips = dst_Endpoint.split('/')
    session.httpPost("config/ixchariot/appMixes/1/network/destinationEndpoints", data =
ixchariotApi.createEndpoint(ips[0], ips[1]))

# Add applications to the AppMix

#                               appName                               appRatio
appList = [
                                ["Facebook",
                                10],
                                ["Yahoo Mail",
                                40],
                                ["YouTube Enterprise", 50]
                                ]

for i in range(0, len(appList)):
    appData = appList[i]
    appName = appData[0]
    appRatio = appData[1]
    appScript = ixchariotApi.getApplicationScriptFromResourcesLibrary(session, appName)
    app = ixchariotApi.createApp(appScript, appRatio);
    session.httpPost("config/ixchariot/appMixes/1/settings/applications", data = app)

# Create a new FlowGroup
name = "FlowGroup 1"
direction = "SRC_TO_DEST"
topology = "FULL_MESH"
flowgroup = ixchariotApi.createFlowGroup(name, direction, topology)
session.httpPost("config/ixchariot/flowGroups", data = flowgroup)

# Configure endpoints for the FlowGroup

# This demonstrates how to manually assign endpoints to the test configuration using
known IP addresses.
# If you want to assign an endpoint discovered by the Registration Server, use the
ixchariotApi.getEndpointFromResourcesLibrary() function
# to get the data for httpPost
for src_Endpoint in src_EndpointsList:
    ips = src_Endpoint.split('/')
    session.httpPost("config/ixchariot/flowGroups/1/network/sourceEndpoints", data =
ixchariotApi.createEndpoint(ips[0], ips[1]))
for dst_Endpoint in dst_EndpointsList:
    ips = dst_Endpoint.split('/')
```

```
session.httpPost("config/ixchariot/flowGroups/1/network/destinationEndpoints", data
= ixchariotApi.createEndpoint(ips[0], ips[1]))

# Add flows to the FlowGroup

#                                     flowName,                                     users,

flowList = [

    # Data flows
    ["TCP Baseline Performance",      1,      "TCP",
    ["UDP Baseline Performance",      3,      "UDP",

    # VoIP flows
    ["G.711a (64 kbps)",              1,      "RTP"

    # Video over RTP flows
    ["RTP HD (10 Mbps)",              1,      "RTP"

    # Adaptive video over HTTP flows
    ["Netflix Video SD",              1,      "TCP"

    ]

for i in range (0, len(flowList)):
    flowData = flowList[i]
    flowName = flowData[0]
    users = flowData[1]
    protocol = flowData[2]
    sourceQoSName = flowData[3]
    destinationQoSName = flowData[4]
    flowScript = ixchariotApi.getFlowScriptFromResourcesLibrary(session, flowName)

    # Example for changing the parameter values
    if i == 3:
        ixchariotApi.changeFlowScriptParameterValue(flowScript, "Bit Rate", "9.8 Mbps"

    if i == 4:
        ixchariotApi.changeFlowScriptParameterValue(flowScript, "Segment Duration (s)"
"3")

    sourceQoSTemplate = ixchariotApi.getQoSTemplateFromResourcesLibrary(session,
sourceQoSName)
    destinationQoSTemplate = ixchariotApi.getQoSTemplateFromResourcesLibrary(session,
destinationQoSName)

    flow = ixchariotApi.createFlow(flowScript, users, protocol, sourceQoSTemplate,
```

```
destinationQoSTemplate)
    session.httpPost("config/ixchariot/flowGroups/1/settings/flows", data = flow)

# Create a new MulticastGroup
name = "MulticastGroup 1"
mcastgroup = ixchariotApi.createMulticastGroup(name)
session.httpPost("config/ixchariot/multicastGroups", data = mcastgroup)

# Configure endpoints for the MulticastGroup
src_EndpointsList = ["192.168.1.100/192.168.1.101"]
dst_EndpointsList = ["192.168.1.200/192.168.1.201", "192.168.1.210/192.168.1.211"]

# This demonstrates how to manually assign endpoints to the test configuration using
known IP addresses.
# If you want to assign an endpoint discovered by the Registration Server, use the
ixchariotApi.getEndpointFromResourcesLibrary() function
# to get the data for httpPost
for src_Endpoint in src_EndpointsList:
    ips = src_Endpoint.split('/')
    session.httpPost("config/ixchariot/multicastGroups/1/network/sourceEndpoints", data
= ixchariotApi.createEndpoint(ips[0], ips[1]))
for dst_Endpoint in dst_EndpointsList:
    ips = dst_Endpoint.split('/')
    session.httpPost("config/ixchariot/multicastGroups/1/network/destinationEndpoints",
data = ixchariotApi.createEndpoint(ips[0], ips[1]))

# Add multicast flows to the MulticastGroup

#                                     mcastFlowName,                                     mcastAddress:Port,

mcastFlowList = [
                                     ["Skype-Video-180p",      "224.1.1.1:5000",      "UDP"
                                     ["RTP HD (10 Mbps)",      "224.1.1.2:6000",      "RTP"
                                     ]

for i in range (0, len(mcastFlowList)):
    mcastFlowData = mcastFlowList[i]
    flowName = mcastFlowData[0]
    mcastAddressPort = mcastFlowData[1]
    protocol = mcastFlowData[2]
    sourceQoSName = mcastFlowData[3]
    flowScript = ixchariotApi.getFlowScriptFromResourcesLibrary(session, flowName)
    sourceQoSTemplate = ixchariotApi.getQoSTemplateFromResourcesLibrary(session,
sourceQoSName)
    mcastFlow = ixchariotApi.createMulticastFlow(flowScript, mcastAddressPort,
```

```
protocol, sourceQoSTemplate)
    session.httpPost("config/ixchariot/multicastGroups/1/settings/flows", data =
mcastFlow)

# As an alternative to creating the test configuration from scratch, you can use
ixchariotApi.loadConfigFromResourcesLibrary()
# to load an existing configuration into the given session, or ixchari-
otApi.importConfigFromFileToResourcesLibrary() followed
# by ixchariotApi.loadConfigFromResourcesLibrary() to use a test configuration file
from disk.

try:
    print "Starting the test..."
    # This is a blocking function which starts the test and waits for it to end
    result = session.runTest()

    print "The test ended"

    # Save all results to CSV files.
    print "Saving the test results into zipped CSV files...\n"
    filePath = "testResults.zip"
    with open(filePath, "wb+") as statsFile:
        api.getStatsCsvZipToFile(result.testId, statsFile)

    # Get results after test run.
    #
    # NOTE: The functions below can also be used to retrieve statistics while the test
is running:
    # - start the test with the non-blocking function session.startTest() instead of
the blocking session.runTest()
    # - run a loop until the session.testIsRunning property becomes false
    # - inside the loop, use the functions below to retrieve the results collected up
to that point
    #         (use time.sleep() to call them at regular intervals)

    # Get test level results.
    # NOTE: use the statistics names from the CSV report (ixchariot.csv)
    results = ixchariotApi.getTestLevelResults(session, ["Throughput"])

    print "Test Level Results: \n"
    for res in results:
        # Each object in the list of results is of type Statistic (contains the statis
name and a list of StatisticValue objects).
        print res.name
```

```
        for val in res.values:
            # The list will contain StatisticValue objects for all the reported ti
since the beginning of the test.
            # Each StatisticValue object contains the timestamp and the actual val
            print str(val.timestamp) + "          " + str(val.value)
        print ""

# Get group level results.
# NOTE: use the statistics names from the CSV report (ixchariot_mix.csv)
results = ixchariotApi.getGroupLevelResults(session, ["Throughput"], "AppMix 1")

print "Group Level Results for AppMix 1:\n"
for res in results:
    # Each object in the list of results has a printing function defined.
    # It will print the name of the statistic and the list of timestamp - value pa
    # For accessing each of these components separately see the example above.
    print res
    print ""

# Get flow level results
# NOTE: use the statistics names from the CSV report (ixchariot_mix_applic-
ation.csv)
results = ixchariotApi.getFlowLevelResults(session, ["Throughput", "Total Datagrams
Sent"], "FlowGroup 1", "RTP HD (10 Mbps)", "RTP")

print "Flow Level Results for RTP HD (10 Mbps) (RTP) from FlowGroup 1:\n"
for res in results:
    print res
    print ""

# Get user level results for the first user
# NOTE: use the statistics names from the CSV report (ixchariot_mix_application_
user.csv)
results = ixchariotApi.getUserLevelResultsFromFlow(session, ["Throughput"],
"FlowGroup 1", "RTP HD (10 Mbps)", "RTP", 1)

print "User Level Results for the first user in flow RTP HD (10 Mbps) (RTP),
FlowGroup 1:\n"
for res in results:
    print res
    print ""

# Get User Info results for the first user
# NOTE: use the statistics names from the CSV report (ixchariot_user_info.csv)
results = ixchariotApi.getUserInfoFromFlow(session, ["Direction", "Source Endpoint
```

```
OS", "Error"], "FlowGroup 1", "RTP HD (10 Mbps)", "RTP", 1)

    print "User Info Results for the first user in flow RTP HD (10 Mbps) (RTP),
FlowGroup 1:\n"
    for res in results:
        print res
        print ""

except Exception, e:
    print "Error", e

print "Stopping the session..."
session.stopSession()

print "Deleting the session..."
session.httpDelete()
```

ixchariotApi.py

```
from ixia.webapi import *

def getResourceFromLibrary(session, resourceCategory, resourceName):
    resources = session.parentConvention.httpGet("ixchariot/resources/" + resourceCategory)
    for i in range (0, len(resources)):
        resource = resources[i]
        if resourceName == resource.name:
            return resource
    return None

def getEndpointFromResourcesLibrary(session, endpointName):
    return getResourceFromLibrary(session, "endpoint", endpointName)

def getQoSTemplateFromResourcesLibrary(session, qosTemplateName):
    if qosTemplateName == "None":
        qosTemplate = WebObjectBase()
        qosTemplate.name = "None"
        qosTemplate.serviceType = "BEST_EFFORT"
        qosTemplate.type = "NO_QOS"
    else:
        qosTemplate = getResourceFromLibrary(session, "qostemplate", qosTemplateName)
    return qosTemplate

def getFlowScriptFromResourcesLibrary(session, flowName):
    return getResourceFromLibrary(session, "flowscript", flowName)
```



```
def getApplicationScriptFromResourcesLibrary(session, applicationName):
    return getResourceFromLibrary(session, "applicationscript", applicationName)

def getFlowScriptParameter(flowScript, parameterName):
    for i in range (0, len(flowScript.scriptParameters)):
        parameter = flowScript.scriptParameters[i]
        if parameterName == parameter.caption:
            return parameter
    return None

def changeFlowScriptParameterValue(flowScript, parameterName, parameterValue):
    parameter = getFlowScriptParameter(flowScript, parameterName)
    parameter.value = parameterValue

def createFlowGroup(name, direction, topology):
    flowGroup = WebObjectBase()
    flowGroup.network = createNetwork(direction, topology)
    flowGroup.settings = createFlowGroupSettings(name)
    return flowGroup

def createMulticastGroup(name):
    flowGroup = WebObjectBase()
    flowGroup.network = createNetwork("SRC_TO_DEST", "MULTICAST")
    flowGroup.settings = createMulticastGroupSettings(name)
    return flowGroup

def createApplicationMix(name, distributionType, noUsers, direction, topology):
    appMix = WebObjectBase()
    appMix.network = createNetwork(direction, topology)
    appMix.settings = createApplicationMixSettings(name, distributionType, noUsers)
    return appMix

def createNetwork(direction, topology):
    network = WebObjectBase()
    network.enabled = True
    network.direction = direction
    network.topology = topology
    return network

def createFlowGroupSettings(name):
    settings = WebObjectBase()
    settings.name = name
    return settings

def createMulticastGroupSettings(name):
```

```
settings = WebObjectBase()
settings.name = name
return settings

def createApplicationMixSettings(name, distributionType, users):
    settings = WebObjectBase()
    settings.name = name
    settings.distributionType = distributionType
    settings.numberOfUsers = users
    return settings

def createFlow(script, users, protocol, sourceQoS, destinationQoS):
    flow = WebObjectBase()
    flow.script = script
    flow.numberOfUsers = users
    flow.protocol = protocol
    flow.sourceQoS = sourceQoS
    flow.destinationQoS = destinationQoS
    return flow

def createMulticastFlow(script, multicastAddrPort, protocol, sourceQoS):
    mcastFlow = WebObjectBase()
    mcastFlow.script = script
    mcastFlow.multicastIp = multicastAddrPort
    mcastFlow.protocol = protocol
    mcastFlow.sourceQoS = sourceQoS
    return mcastFlow

def createApp(script, ratio):
    app = WebObjectBase()
    app.script = script
    app.ratio = ratio
    return app

def createEndpoint(testIP, mgmtIP):
    endpoint = WebObjectBase()
    endpoint.ips = []
    endpoint.ips.append(createIP(testIP)) # this example demonstrates just 1 test IP,
but it's also possible to add multiple test IPs to the list
    endpoint.managementIp = createIP(mgmtIP)
    endpoint.name = mgmtIP # it's also possible to pass the endpoint name as a para-
meter to the function
    return endpoint

def getIPType(ip):
```

```
        if ip.find(":") != -1:
            return "IPv6"
        else:
            return "IPv4"

def createIP(ip_address):
    ip = WebObjectBase()
    ip.address = ip_address
    ip.type = getIPType(ip_address)
    return ip

def saveConfigToResourcesLibrary(session, configName):
    session.saveConfiguration(configName)

def loadConfigFromResourcesLibrary(session, configName):
    session.loadConfiguration(configName)

def exportConfigFromResourcesLibraryToFile(session, configName, filePath):
    # filePath must have the ".ixcfg" extension
    with open(filePath, "wb+") as exportFile:
        session.exportConfigurationToFile(configName, exportFile)

def importConfigFromFileToResourcesLibrary(session, filePath):
    # filePath must have the ".ixcfg" extension (for configs exported from IxChariot
    9.3 or newer) or the ".zip" extension (for configs exported from IxChariot 8.0 -
    9.2)
    with open(filePath, "rb") as importFile:
        importedConfig = session.importConfigurationFromFile(importFile)
        importedConfigName = importedConfig.details.name
        return importedConfigName

def deleteOldestTestResults(apiConnection, userName, howManyTestsToDelete):
    testResults = apiConnection.httpGet("results", params = {"start" : 0, "limit" :
    howManyTestsToDelete, "sortColumn" : "starttime", "sortOrder" : "ascending", "fil-
    ter" : "userid:%s" % userName})
    for testResult in testResults.testRunInformationList:
        apiConnection.httpDelete("results/%d" % testResult.testRunId)

class StatisticValue:
    """Describes a value for a statistic at a moment in time.
    @param timestamp:      the moment in the test when the value was recorded.
    @param value:          the actual value recorded.
    """
    def __init__(self, timestamp, value):
```

```
        self.timestamp = timestamp
        if value == None:
            self.value = "N/A"
        else:
            self.value = value

class Statistic:
    """Describes a statistic from the test.
    @param name:        the name of the statistic.
    @param values:       the list of values for that statistic in time.
    """

    def __init__(self, name):
        self.name = name
        self.values = []

    def __str__(self):
        res = self.name + ":\n"
        for val in self.values:
            res = res + str(val.timestamp) + "    " + str(val.value) + "\n"
        return res

    def add_value(self, value):
        self.values.append(value)

def getRawResults(session, dataObject, stats, filter, filterErrorMessage):
    try:
        statsList = WebListProxy([WebObjectProxy(definition = "{" + dataObject + ":" +
stat + "}") for stat in stats])
        query = WebObjectProxy(stats=statsList, cacheSize=100000, filter=filter)
        channel = session.httpPost("stats/channels", WebObjectProxy(timeToLive=120), headers={"Content-Type" : "application/json", "Accept" : "application/json"})
        query = session.httpPost("stats/channels/%d/queries" % channel.id, query, headers={"Content-Type" : "application/json", "Accept" : "application/json"})
        requestResult = session.httpPost("stats/channels/%d/requests" % channel.id, WebObjectProxy(count=100000))
        valuesList = requestResult.data.map.__dict__[query.id]
    except:
        raise ValueError(filterErrorMessage)
    finally:
        try:
            session.httpDelete("stats/channels")
        except:
            pass
```

```
        return (valuesList, query)

def getResults(session, dataObject, stats, filter, filterErrorMessage):
    (valuesList, query) = getRawResults(session, dataObject, stats, filter, filterErrorMessage)

    statsResults = []
    for i in range(0, len(stats)):
        result = Statistic(stats[i])
        for j in range(0, len(valuesList)):
            value = valuesList[j]

            if len(value.values) == 0:
                raise ValueError(filterErrorMessage)

            statValue = StatisticValue(value.timestamp, value.values[0][i])
            result.add_value(statValue)
        statsResults.append(result)

    return statsResults

def getTestLevelIndexOfFirstUserForGroupApp(session, group, app, filterErrorMessage):
    # Create a filter that will return all the users associated with the given group
    # and app, for the first timestamp
    filter = WebObjectProxy(
        type = 'boolean',
        leftItem = WebObjectProxy(
            type = 'boolean',
            leftItem = "ixchariot:mix",
            operator = '=',
            rightItem = group),
        operator = 'and',
        rightItem = WebObjectProxy(
            type = 'boolean',
            leftItem = WebObjectProxy(
                type = 'boolean',
                leftItem = "ixchariot:app",
                operator = '=',
                rightItem = app),
            operator = 'and',
            rightItem = WebObjectProxy(
                type = 'boolean',
                leftItem = "ixchariot:timestamp",
                operator = '<',
                rightItem = "ixchariot:timestamp")),
        type = 'boolean',
        leftItem = "ixchariot:timestamp",
        operator = '<',
        rightItem = "ixchariot:timestamp")

    try:
```

```
(valuesList, query) = getRawResults(session, "ixchariot", ["user"], filter, filterErrorMessage)

# Get the test-level index of the first user for this group and app
userIndex = min(valuesList[0].values, key=lambda row : int(row[0]))[0]
except:
    raise ValueError(filterErrorMessage)

return userIndex

def getTestLevelIndexOfFirstUserForGroupAppFromUserInfo(session, group, app, filterErrorMessage):
    # Create a filter that will return all the users associated with the given group
    and app, for the first timestamp
    filter = WebObjectProxy(
        type = 'boolean',
        leftItem = WebObjectProxy(
            leftItem = "ixchariot_user_info",
            operator = '=',
            rightItem = group),
        operator = 'and',
        rightItem = WebObjectProxy(
            leftItem = "ixchariot_user_info",
            operator = '=',
            rightItem = app))

    try:
        (valuesList, query) = getRawResults(session, "ixchariot_user_info", ["User"], filter, filterErrorMessage)

        # Get the test-level index of the first user for this group and app
        userIndex = min(valuesList[0].values, key=lambda row : int(row[0]))[0]
    except:
        raise ValueError(filterErrorMessage)

    return userIndex

def getTestLevelResults(session, stats):
    """Gets test level results for the specified statistics.

    Can be used during the test run or after the test has ended.
    Will return all available results, since the beginning of the test.

    @param session: the current session where test is running / loaded
    @param stats: the list of statistics names to get the values for (use the
```

statistics names from the CSV report - ixchariot.csv)

@return a list of Statistic objects (one object for each request)
Each Statistic object contains a list of StatisticValue objects.

Each StatisticValue object contains a StatisticValue object.
This function will return all the available statistics.
values collected since the beginning of the test.
Statistic and StatisticValue classes for details.

```
@exception ValueError  
"""
```

```
filterErrorMessage = "No statistics were reported for this test"  
return getResults(session, "ixchariot", stats, None, filterErrorMessage)
```

```
def getGroupLevelResults(session, stats, group):
```

```
    """Gets group level results for the specified statistics.
```

```
    Can be used during the test run or after the test has ended.  
    Will return all available results, since the beginning of the test.
```

```
    @param session: the current session where test is running / loaded  
    @param stats: the list of statistics names to get the values for (use the statistics names from the CSV report - ixchariot_mix.csv)  
    @param group: the app mix/flow group/multicast group to get the stats for
```

@return a list of Statistic objects (one object for each request)
Each Statistic object contains a list of StatisticValue objects.

Each StatisticValue object contains a StatisticValue object.
This function will return all the available statistics.
values collected since the beginning of the test.
Statistic and StatisticValue classes for details.

```
@exception ValueError  
"""
```

```
filter = WebObjectProxy(leftItem = "ixchariot:mix", operator = "=", rightItem = group)  
filterErrorMessage = "Could not find any values for mix/group " + group  
return getResults(session, "ixchariot", stats, filter, filterErrorMessage)
```

```
def getAppLevelResults(session, stats, group, app):
```

```
    """Gets application level results for the specified statistics.
```

```
    Can be used during the test run or after the test has ended.
```

Will return all available results, since the beginning of the test.

```
@param session:      the current session where test is running / loaded
@param stats:        the list of statistics names to get the values for (use the st
istics names from the CSV report - ixchariot_mix_application.csv)
@param group:        the app mix that contains the app
@param app:          the app to get the stats for
```

```
@return              a list of Statistic objects (one object for each reque
Each Statistic object contains a list of StatisticValue objects.
```

```
Each StatisticValue object contains a statisti
This function will return all the available statistic
values collected since the beginning of the te
Statistic and StatisticValue classes for details.
```

```
@exception ValueError
"""
```

```
filter = WebObjectProxy(
    type = 'boolean',
    leftItem = WebObjectProxy(
        leftItem = "ixchariot:mix",
        operator = '=',
        rightItem = group),
    operator = 'and',
    rightItem = WebObjectProxy(
        leftItem = "ixchariot:applicat
        operator = '=',
        rightItem = app))
filterErrorMessage = "Could not find any values for mix/group " + group + " and
app/flow " + app
return getResults(session, "ixchariot", stats, filter, filterErrorMessage)
```

```
def getFlowLevelResults(session, stats, group, flow, protocol):
```

```
    """Gets flow level results for the specified statistics.
```

```
Can be used during the test run or after the test has ended.
Will return all available results, since the beginning of the test.
```

```
@param session:      the current session where test is running / loaded
@param stats:        the list of statistics names to get the values for (use the st
istics names from the CSV report - ixchariot_mix_application.csv)
@param group:        the flow group / multicast group that contains the flow
@param flow:         the flow to get the stats for
@param protocol:     the test protocol for the flow
```



```
@return                                a list of Statistic objects (one object for each request)
Each Statistic object contains a list of StatisticValue objects.
                                Each StatisticValue object contains a StatisticValue object
This function will return all the available statistics
                                values collected since the beginning of the test
Statistic and StatisticValue classes for details.

@exception ValueError
"""

fullFlowName = flow + " (" + protocol + ")"
return getAppLevelResults(session, stats, group, fullFlowName)

def getUserLevelResultsFromApp(session, stats, group, app, user):
    """Gets user level results for the specified statistics.

    Can be used during the test run or after the test has ended.
    Will return all available results, since the beginning of the test.

    @param session:        the current session where test is running / loaded
    @param stats:          the list of statistics names to get the values for (use the statistics names from the CSV report - ixchariot_mix_application_user.csv)
    @param group:          the app mix that contains the app
    @param app:            the app to get the stats for
    @param user:           which user from the app to get results for (a number between 1 and the number of users in the app)

    @return                a list of Statistic objects (one object for each request)
    Each Statistic object contains a list of StatisticValue objects.
                                Each StatisticValue object contains a StatisticValue object
    This function will return all the available statistics
                                values collected since the beginning of the test
    Statistic and StatisticValue classes for details.

    @exception ValueError
    """

    filterErrorMessage = "Could not find any values for mix/group " + group + ", app/-flow " + app + " and user " + str(user)

    # The user index we receive as input parameter is relative to this group and app
    # We need to convert it to the test-level index
    # (the user index as seen in UI or CSV, taking into account the users from the other groups and apps)
```

```
testLevelUserIndex = int(getTestLevelIndexOfFirstUserForGroupApp(session, group,
app, filterErrorMessage)) + user - 1

filter = WebObjectProxy(
    type = 'boolean',
    leftItem = WebObjectProxy(
        leftItem = "ixchariot:mix",
        operator = '=',
        rightItem = group),
    operator = 'and',
    rightItem = WebObjectProxy(
        type = 'boolean',
        leftItem = WebObjectProxy(
            operator = 'and',
            rightItem = WebObjectProxy(

return getResults(session, "ixchariot", stats, filter, filterErrorMessage)

def getUserLevelResultsFromFlow(session, stats, group, flow, protocol, user):
    """Gets user level results for the specified statistics.

    Can be used during the test run or after the test has ended.
    Will return all available results, since the beginning of the test.

    @param session:      the current session where test is running / loaded
    @param stats:        the list of statistics names to get the values for (use the st
istics names from the CSV report - ixchariot_mix_application_user.csv)
    @param group:        the flow group / multicast group that contains the flow
    @param flow:         the flow to get the stats for
    @param protocol:     the test protocol for the flow
    @param user:         which user from the flow to get results for (a number between
the number of users in the flow)

    @return              a list of Statistic objects (one object for each reques
Each Statistic object contains a list of StatisticValue objects.
                        Each StatisticValue object contains a statisti
This function will return all the available statistic
                        values collected since the beginning of the te
Statistic and StatisticValue classes for details.
```

```

@exception ValueError
"""

fullFlowName = flow + " (" + protocol + ")"
return getUserLevelResultsFromApp(session, stats, group, fullFlowName, user)

def getUserInfoFromApp(session, stats, group, app, user):
    """Gets User Info for the specified statistics (e.g. Name, Location, Version, Oper-
    ating System, IP addresses and errors for the source and destination endpoints).

    Can be used during the test run or after the test has ended.

    @param session:      the current session where test is running / loaded
    @param stats:        the list of statistics names to get the values for (use the st
    istics names from the CSV report - ixchariot_user_info.csv)
    @param group:        the app mix that contains the app
    @param app:          the app to get the stats for
    @param user:         which user from the app to get results for (a number between 1
    the number of users in the app)

    @return              a list of Statistic objects (one object for each reque
    Each Statistic object contains a list with one StatisticValue object.
                        The StatisticValue object contains a statistic
    definition of the Statistic and StatisticValue classes for details.
                        Unlike the other statistics, the User Info res
    timestamp. Timestamp 0 is arbitrarily used to keep the same API
                        as for the other statistics. During the test e
    might be added or updated (by overwriting the previous values).

    @exception ValueError
    """

    filterErrorMessage = "Could not find any values for mix/group " + group + ", app/-
    flow " + app + " and user " + str(user)

    # The user index we receive as input parameter is relative to this group and app
    # We need to convert it to the test-level index
    # (the user index as seen in UI or CSV, taking into account the users from the oth-
    ers groups and apps)
    testLevelUserIndex = int(getTestLevelIndexOfFirstUserForGroupAppFromUserInfo(ses-
    sion, group, app, filterErrorMessage)) + user - 1

    filter = WebObjectProxy(
        type = 'boolean',
        leftItem = WebObjectProxy(

```



```
fullFlowName = flow + " (" + protocol + ")"
return getUserInfoFromApp(session, stats, group, fullFlowName, user)
```

Accessing the API

The IxChariot WebAPI library is exposed through the `ixia.webapi` module. To use it in a script, you import it using the name `ixia.webapi`.

For example:

```
import ixia.webapi as webapi
```

Connection Methods

To...	Use...
Create a session	createSession
Get the list of saved test configurations	getConfigurations
Get the list of sessionIds for current sessions	getSessions
Get the list of allowed session types	getSessionTypes
Retrieve a set of statistics and store them in a ZIP file	getStatsCsvZipToFile
Return an existing session	joinSession

createSession

Creates and returns a session of the given type. On creation, sessions are put into the "Initial" state. After being created, sessions must be started.

Return Value

Session

Syntax

```
createSession(sessionType: string)
```

Parameters

sessionType	Type of session to create: ixchariot: IxChariot application
-------------	--

getConfigurations

Returns a list of objects that have name and description properties for all saved configurations.

Return Value

Configuration list

Syntax

```
getConfigurations()
```

Parameters

None.

getSessions

Returns a list of session IDs for sessions that currently exist.

Return Value

SessionData list

Syntax

```
getSessions()
```

Parameters

None

getSessionTypes

Returns a list of strings allowed for the `sessionType` field of [createSession](#).

Return Value

String list

Syntax

```
getSessionTypes()
```

Parameters

None

getStatsCsvZipToFile

Retrieves a test's entire set of statistics from the web server and writes them to the file-like object `statFile`.

Return Value

None

Syntax

```
getStatsCsvToFile(testOrResultId : int, statFile : fileHandle)
```

Parameters

<code>testOrResultId</code>	ID of the test to retrieve statistics for. For example, the ID is returned as the <code>id</code> property of the return value from <code>runTest</code> .
<code>statFile</code>	File handle or file-like object to write the CSV-formatted statistics data files to, in ZIP-archive format

joinSession

Returns an existing session.

Return Value

Session

Syntax

```
joinSession(sessionId: int)
```

Parameters

<code>sessionId</code>	Session to join.
------------------------	------------------

IxChariotApi Methods

To...	Use...
Modify the value of a flow parameter	changeFlowScriptParameterValue
Create an application	createApp
Create an application mix	createApplicationMix

To...	Use...
Create an endpoint	createEndpoint
Create a flow	createFlow
Create a flow group	createFlowGroup
Create a multicast flow	createMulticastFlow
Create a multicast group	createMulticastGroup
Delete test results from previous runs	deleteOldestTestResults
Save a test configuration from the resources library to a file	exportConfigFromResourcesLibraryToFile
Retrieve application level results	getAppLevelResults
Get an application from the resources library	getApplicationScriptFromResourcesLibrary
Get the list of endpoints from the resources library (including the ones discovered by the Registration Server)	getEndpointFromResourcesLibrary
Retrieve flow/multicast flow level results	getFlowLevelResults
Get a flow from the resources library	getFlowScriptFromResourcesLibrary
Retrieve group/mix level results	getGroupLevelResults
Get the list of QoS templates from the resources library	getQoSTemplateFromResourcesLibrary
Retrieve test level results	getTestLevelResults
Retrieve user level results from an application	getUserLevelResultsFromApp
Retrieve user level results from a flow	getUserLevelResultsFromFlow
Get user info for the specified statistics from an application	getUserInfoFromApp
Get user info for the specified statistics from a flow	getUserInfoFromFlow
Load a test configuration from a file to the resources library	importConfigFromFileToResourcesLibrary

To...	Use...
Load a test configuration from the resources library	loadConfigFromResourcesLibrary
Save a test configuration to the resources library	saveConfigToResourcesLibrary

createApp

Creates and returns a new application with the given characteristics.

Return Value

The new application, as a WebObject.

Syntax

```
createApp(script, ratio)
```

Parameters

script	The application to use when running tests, obtained using <code>getApplicationScriptFromResourcesLibrary</code>
ratio	The proportion of traffic that the application is assigned within the application mix

createApplicationMix

Creates and returns a new application mix with the given characteristics.

Return Value

The new application mix, as a WebObject

Syntax

```
createApplicationMix(name, distributionType, noUsers, direction, topology)
```

Parameters

name	The name of the new application mix
------	-------------------------------------

distributionType	One of the following: <ul style="list-style-type: none">• "USERS"• "THROUGHPUT" See the <i>IxChariot User Guide</i> for the characteristics of each distribution type.
noUsers	Overall number of users for the application mix
direction	One of: <ul style="list-style-type: none">• "SRC_TO_DEST" – for traffic flowing from source to destination• "DEST_TO_SRC" – for traffic flowing from destination to source
topology	One of: <ul style="list-style-type: none">• "FULL_MESH" – for creating full-mesh connections between source and destination endpoints• "ROUND_ROBIN" – for creating one-to-one connections between source and destination endpoints

createEndpoint

Creates and returns an endpoint with the given characteristics.

Return Value

The new endpoint, as a WebObject.

Syntax

```
createEndpoint(testIP, mgmtIP)
```

Parameters

testIP	The IP to be used for test traffic for the new endpoint
mgmtIP	The IP to be used for management traffic for the new endpoint

createFlow

Creates and returns a new flow with the given characteristics.

Return Value

The new flow, as a WebObject

Syntax

```
createFlow(script, users, protocol, sourceQoS, destinationQoS)
```

Parameters

script	The flow to use for running tests, obtained using <code>getFlowScriptFromResourcesLibrary</code>
users	The number of users for the flow
protocol	One: <ul style="list-style-type: none">• "TCP"• "UDP"• "RTP" Depending on the flow, some of these options may not be valid. For example, for a UDP Baseline Performance flow, you cannot set TCP.
sourceQoS	The QoS template to use in the test for the source endpoint, obtained using <code>getQoSTemplateFromResourcesLibrary</code>
destinationQoS	The QoS template to use in the test for the destination endpoint, obtained using <code>getQoSTemplateFromResourcesLibrary</code>

createFlowGroup

Creates and returns a flow group with the given characteristics.

Return Value

The new flow group, as a WebObject.

Syntax

```
createFlowGroup(name, direction, topology)
```

Parameters

name	The name of the new flow group
direction	One of the following: <ul style="list-style-type: none">• "SRC_TO_DEST" – for traffic flowing from source to destination• "DEST_TO_SRC" – for traffic flowing from destination to source• "BOTH" – for traffic flowing in both directions
topology	One of the following: <ul style="list-style-type: none">• "FULL_MESH" – for creating full mesh connections between source and destination endpoints• "ROUND_ROBIN" – for creating one-to-one connections between source and destination endpoints

createMulticastFlow

Creates and returns a new multicast flow with the given characteristics.

Return Value

The new multicast flow, as a WebObject.

Syntax

```
createMulticastFlow(script, multicastAddrPort, protocol, sourceQoS)
```

Parameters

script	The flow to use when running tests, obtained using <code>getFlowScriptFromResourcesLibrary</code>
multicastAddrPort	The multicast address and port, in the address:port format
protocol	One of: <ul style="list-style-type: none">• "UDP"• "RTP"
sourceQoS	The QoS template to use in the test for the source endpoint, obtained using <code>getQoSTemplateFromResourcesLibrary</code>

createMulticastGroup

Creates and returns a multicast group with the given name. The topology for the new group will be set to "MULTICAST" and the direction of the traffic will be "SRC_TO_DEST".

Return Value

The new multicast group, as a WebObject

Syntax

```
createMulticastGroup(name)
```

Parameters

name	The name of the new multicast group
------	-------------------------------------

changeFlowScriptParameterValue

Modifies the value of a flow parameter

Syntax

```
changeFlowScriptParameterValue(flowScript, parameterName, parameterValue)
```

Parameters

<code>flowScript</code>	The flow whose parameter to modify, obtained using <code>getFlowScriptFromResourcesLibrary</code>
<code>parameterName</code>	The flow parameter to modify
<code>parameterValue</code>	The parameter value to modify

deleteOldestTestResults

Deletes test results from the resources library for the specified user.

NOTE

Depending on the number of test results, the process might take up to several minutes.

Return Value

None

Syntax

```
deleteOldestTestResults(apiConnection, userName, howManyTestsToDelete)
```

Parameters

<code>apiConnection</code>	The object returned by <code>webApi.connect()</code>
<code>userName</code>	The user name for which to delete the test results
<code>howManyTestsToDelete</code>	How many test results to delete (starting from older to newer)

exportConfigFromResourcesLibraryToFile

Exports a test configuration from the resources library to a file.

Return Value

None

Syntax

```
exportConfigFromResourcesLibraryToFile(session, configName, filePath)
```

Parameters

session	The current IxChariot session
configName	The name of the configuration to export. The configuration must already exist in the resources library.
filePath	The path and filename where to export the configuration. The file must have the .ixcfg extension.

getAppLevelResults

Retrieves application-level results for the specified statistics. Can be used during the test run or after the test has ended. Will return all available results since the beginning of the test.

Return Value

A list of Statistic objects (one object for each requested statistic). Each Statistic object contains a list of StatisticValue objects.

Each StatisticValue object contains a statistic value at a specific timestamp. This function will return all the available statistic values collected since the beginning of the test. For details, see the definition of the [Statistic](#) and [StatisticValue](#) classes.

Syntax

```
getAppLevelResults(session, stats, group, app)
```

Parameters

session	The current IxChariot session where the test is running/loaded
stats	The list of statistics names for which to get the values. The names should be identical to those in the results CSV.
group	The application mix that contains the application
app	The application for which to retrieve the results

getApplicationScriptFromResourcesLibrary

Looks up the requested application in the resource library and returns it.

Return Value

The requested application, or 'None' if the application was not found.

Syntax

```
getApplicationScriptFromResourcesLibrary(session, applicationName)
```

Parameters

session	The current IxChariot session
applicationName	The name of the application to retrieve from the resources library

getEndpointFromResourcesLibrary

Looks up the requested endpoint in the resource library and returns it.

Return Value

The requested endpoint, or 'None' if the endpoint was not found.

Syntax

```
getEndpointFromResourcesLibrary(session, endpointName)
```

Parameters

session	The current IxChariot session
endpointName	The name of the endpoint to retrieve from the resources library

getFlowLevelResults

Retrieves flow-level results for the specified statistics. Can be used during the test run or after the test has ended. Will return all available results since the beginning of the test.

Return Value

A list of [Statistic](#) objects (one object for each requested statistic). Each [Statistic](#) object contains a list of [StatisticValue](#) objects.

Each [StatisticValue](#) object contains a statistic value at a specific timestamp. This function will return all the available statistic values collected since the beginning of the test. For details, see the definition of the [Statistic](#) and [StatisticValue](#) classes.

Syntax

```
getFlowLevelResults(session, stats, group, flow, protocol)
```

Parameters

session	The current IxChariot session where the test is running/loaded
stats	The list of statistics names for which to get the values. The names should be identical to those in the results CSV.
group	The flow group/multicast group that contains the flow
flow	The flow for which to retrieve the results
protocol	The test protocol for the flow. One of : <ul style="list-style-type: none">• "TCP"• "UDP"• "RTP"

getFlowScriptFromResourcesLibrary

Looks up the requested flow in the resource library and returns it.

Return Value

The requested flow, or 'None' if the flow was not found.

Syntax

```
getFlowScriptFromResourcesLibrary(session, flowName)
```

Parameters

session	The current IxChariot session
flowName	The name of the flow to retrieve from the resources library

getGroupLevelResults

Retrieves group-level results for the specified statistics. Can be used during the test run or after the test has ended. Will return all available results since the beginning of the test.

Return Value

A list of [Statistic](#) objects (one object for each requested statistic). Each [Statistic](#) object contains a list of [StatisticValue](#) objects.

Each [StatisticValue](#) object contains a statistic value at a specific timestamp. This function will return all the available statistic values collected since the beginning of the test. For details, see the definition of the [Statistic](#) and [StatisticValue](#) classes.

Syntax

```
getGroupLevelResults(session, stats, group)
```

Parameters

session	The current IxChariot session where the test is running/loaded
stats	The list of statistics names for which to get the values.
group	The application mix/flow group/multicast group for which to retrieve the statistics. The names should be identical to those in the results CSV.

getQoSTemplateFromResourcesLibrary

Looks up the requested QoS template in the resource library and returns it.

Return Value

The requested QoS template, or 'None' if the template was not found.

Syntax

```
getQoSTemplateFromResourcesLibrary (session, qosTemplateName)
```

Parameters

session	The current IxChariot session
qosTemplateName	The name of the QoS template to retrieve from the resources library

getTestLevelResults

Retrieves test-level results for the specified statistics. Can be used during the test run or after the test has ended. Will return all available results, since the beginning of the test.

Return Value

A list of Statistic objects (one object for each requested statistic). Each Statistic object contains a list of StatisticValue objects.

Each StatisticValue object contains a statistic value at a specific timestamp. This function will return all the available statistic values collected since the beginning of the test. For details, see the definition of the [Statistic](#) and [StatisticValue](#) classes.

Syntax

```
getTestLevelResults (session, stats)
```

Parameters

session	The current IxChariot session where the test is running/loaded
stats	The list of statistics names for which to get the values. The names should be identical to those in the results CSV.

getUserLevelResultsFromApp

Gets user-level results for the specified statistics, when the user is running an application within an application mix. Can be used during the test run or after the test has ended. Will return all available results since the beginning of the test.

Return Value

A list of `Statistic` objects (one object for each requested statistic). Each `Statistic` object contains a list of `StatisticValue` objects.

Each `StatisticValue` object contains a statistic value at a specific timestamp. This function will return all the available statistic values collected since the beginning of the test. For details, see the definition of the [Statistic](#) and [StatisticValue](#) classes.

Syntax

```
getUserLevelResultsFromApp(session, stats, group, app, user)
```

Parameters

<code>session</code>	The current IxChariot session where the test is running/loaded
<code>stats</code>	The list of statistics names for which to get the values. The names should be identical to those in the results CSV.
<code>group</code>	The application mix that contains the application
<code>app</code>	The application that contains the user
<code>user</code>	The user from the application for which to retrieve the results. The number between 1 and the number of users running the application in the application mix

getUserLevelResultsFromFlow

Gets user-level results for the specified statistics, when the user is running a flow within a flow group/multicast group. Can be used during the test run or after the test has ended. Will return all available results since the beginning of the test.

Return Value

A list of [Statistic](#) objects (one object for each requested statistic). Each [Statistic](#) object contains a list of [StatisticValue](#) objects.

Each [StatisticValue](#) object contains a statistic value at a specific timestamp. This function will return all the available statistic values collected since the beginning of the test. For details, see the definition of the [Statistic](#) and [StatisticValue](#) classes.

Syntax

```
getUserLevelResultsFromFlow(session, stats, group, flow, protocol, user)
```

Parameters

session	The current IxChariot session where the test is running/loaded
stats	The list of statistics names for which to get the values. The names should be identical to those in the results CSV.
group	The flow group/multicast group that contains the flow
flow	The flow for which to get the results
protocol	The test protocol for the flow. One of: <ul style="list-style-type: none">• "TCP"• "UDP"• "RTP"
user	The user from the flow for which to retrieve the results. The number between 1 and the number of users running the flow within the flow group/multicast group.

getUserInfoFromApp

Gets user info for the specified statistics (e.g. Name, Location, Version, Operating System, IP addresses and errors for the source and destination endpoints). Can be used during the test run or after

the test has ended.

Return Value

A list of `Statistic` objects (one object for each requested statistic). Each `Statistic` object contains a list with one `StatisticValue` object.

The `StatisticValue` object contains a statistic value at time stamp 0. For details, see the definition of the [Statistic](#) and [StatisticValue](#) classes.

Unlike the other statistics, the User Info results are not reported per time stamp. Time stamp 0 is arbitrarily used to keep the same API as for the other statistics. During the test execution, some User Info results might be added or updated (by overwriting the previous values).

Syntax

```
getUserInfoFromApp(session, stats, group, app, user)
```

Parameters

<code>session</code>	The current IxChariot session where the test is running/loaded.
<code>stats</code>	The list of statistics names for which to get the values. The names should be identical to those in the results CSV.
<code>group</code>	The application mix that contains the application.
<code>app</code>	The application that contains the user.
<code>user</code>	The user from the application for which to retrieve the results. The number between 1 and the number of users running the application in the application mix.

getUserInfoFromFlow

Gets user info for the specified statistics (e.g. Name, Location, Version, Operating System, IP addresses and errors for the source and destination endpoints). Can be used during the test run or after the test has ended.

Return Value

A list of `Statistic` objects (one object for each requested statistic). Each `Statistic` object contains a list with one `StatisticValue` object.

The `StatisticValue` object contains a statistic value at time stamp 0. For details, see the definition of the [Statistic](#) and [StatisticValue](#) classes.

Unlike the other statistics, the User Info results are not reported per time stamp. Time stamp 0 is arbitrarily used to keep the same API as for the other statistics. During the test execution, some User Info results might be added or updated (by overwriting the previous values).

Syntax

```
getUserInfoFromFlow(session, stats, group, flow, protocol, user)
```

Parameters

<code>session</code>	The current IxChariot session where the test is running/loaded.
<code>stats</code>	The list of statistics names for which to get the values. The names should be identical to those in the results CSV.
<code>group</code>	The flow group/multicast group that contains the flow.
<code>flow</code>	The flow for which to get the results.
<code>protocol</code>	The test protocol for the flow.
<code>user</code>	The user from the flow for which to retrieve the results. The number between 1 and the number of users running the flow in the flow group/multicast group.

importConfigFromFileToResourcesLibrary

Imports a configuration from a file to the resources library.

Return Value

The name of the imported configuration. The names of the configurations in the resources library must be unique. As such, if a name conflict is detected, the name of the current configuration will be changed to ensure uniqueness. In this case, the name returned by the function will be different from the original name of the configuration.

Syntax

```
importConfigFromFileToResourcesLibrary(session, filePath)
```

Parameters

session	The current IxChariot session
filePath	The path to a previously exported configuration. The file must have the .ixcfg extension for configurations exported from IxChariot 9.3 or newer or the .zip extension for configurations exported from IxChariot 9.2 or older (up to 8.0 included).

loadConfigFromResourcesLibrary

Loads a test configuration from the resources library into the current session.

Return Value

None

Syntax

```
loadConfigFromResourcesLibrary(session, configName)
```

Parameters

session	The current IxChariot session
configName	The name of the configuration to load

saveConfigToResourcesLibrary

Saves a test configuration to the resources library, to allow access at a later time.

Return Value

None

Syntax

```
saveConfigToResourcesLibrary(session, configName)
```

Parameters

session	The current IxChariot session
configName	The name under which to save the configuration in the resources library

Session Methods

Sessions have the following methods:

To...	Use...
Check the notification queue	checkNotifications
Collects debug diagnostics	collectDiagnosticsToFile
Delete a configuration	deleteConfiguration
Delete a session	deleteSession
Export a configuration to a file	exportConfigurationToFile
Get the description of a configuration	findConfigurationByName
Get the list of saved test configurations	getConfigurations
Get the list of notifications	getNotifications
Update the properties of the session	httpRefresh
Import a configuration	importConfigurationFromFile
Load a configuration	loadConfiguration
Run the current configuration and wait for it to finish	runTest

To...	Use...
Save the current configuration	saveConfiguration
Start a session	startSession
Start running the current configuration without waiting for it to finish	startTest
Stop a session	stopSession
Stop the current running test	stopTest
Wait for the current test to stop, when it was started with startTest	waitTestStopped

checkNotifications

Checks the notification queue and throws a WebException if it finds any errors. A WebException is a sub-class of the Python Exception class that only the WebAPI throws.

Return Value

WebException on error

Syntax

```
checkNotifications()
```

Parameters

None

collectDiagnosticsToFile

Collects debug diagnostics (potentially, a long process) and delivers them to the file handle or file-like object `diagFile`. `diagFile` must have been opened in binary mode. The contents written to the file are for Ixia's internal use and subject to change without notice, so scripts should not attempt to inspect or manipulate the file contents.

Return Value

None

Syntax

```
collectDiagnosticsToFile(diagFile)
```

Parameters

diagFile	File to store diagnostics in.
----------	-------------------------------

deleteConfiguration

Deletes a configuration

Return Value

None

Syntax

```
deleteConfiguration(name)
```

Parameters

name	Configuration to delete.
------	--------------------------

deleteSession

Stops a session if it is still running, and then deletes it from the server.

NOTE

Deleting the Python Session object does not cause the session on the server to be deleted. You must call `deleteSession` to delete a session.

Return Value

None

Syntax

```
deleteSession()
```

Parameters

None

findConfigurationByName

Returns a WebObject (same as the objects in the list returned by `getConfigurations`) containing the description of the configuration passed in.

Return Value

WebObject

Syntax

```
findConfigurationByName (name)
```

Parameters

name	Configuration to retrieve the description for.
------	--

getConfigurations

Returns a list of WebObjects representing the test configurations saved on the server. Each object in the list has at least the following fields:

id	Configuration ID
name	Name of the configuration
description	Description of the configuration

Return Value

List of WebObjects

Syntax

```
getConfigurations()
```

Parameters

None

getNotifications

Retrieves the list of notifications. The list is cleared when `startTest()` is called.

Return Value

Notification list

Syntax

```
getNotifications()
```

Parameters

None

httpRefresh

Updates the session properties, as described below, from the server. Any script that loops waiting for a property to change must call `httpRefresh --` otherwise the property will never change.

Return Value

None

Syntax

```
httpRefresh()
```

Properties

Property Name	Type	Description
<code>sessionId</code>	Integer	Session ID.
<code>sessionType</code>	String	Type of session.
<code>testIsRunning</code>	Boolean	true if the test is running, else false.
<code>testConfigName</code>	String	Name of the test configuration where the current configuration has been saved to or loaded from.
<code>state</code>	String	Session state. Possible values are: Initial Starting Active Stopping Stopped Dead
<code>subState</code>	String	Session substate. Values vary based on <code>sessionType</code> and <code>session state</code> . For example, an Active session state may show substates that reflect the test controller state (such as Unconfigured, Configuring, Running, etc.).
<code>creationDate</code>	String	Date and time, in ISO 8601 format, that the session was created.

<code>creationTime</code>	Integer	Epoch time (seconds since 1/1/1970) when the session was created.
<code>startingTime</code>	Integer	Epoch time (seconds since 1/1/1970) when the session was started.
<code>elapsedTime</code>	Integer	Number of seconds elapsed since the session was started.
<code>stoppingTime</code>	Integer	Epoch time (seconds since 1/1/1970) when the session was stopped.

runTest

Runs the current configuration. Nothing is returned until the test run has completed. The result contains, at a minimum, a field named `id` with the `testId` of the test run (as might be required for other method calls like `getStatsCsvToFile`).

Return Value

WebObject

Syntax

```
runTest()
```

Parameters

None

startSession

Starts the session and waits for it to finish starting. While it is starting, the session is in the *Starting* state. When it is finished starting, it is in the *Active* state. Sessions must be in the *Active* state to run tests.

Return Value

None

Syntax

```
startSession()
```

Parameters

None

startTest

Starts running the current configuration and returns immediately. You can use the property `testIsRunning` to determine if the test is still running after calling `startTest`. `startTest` returns the same `WebObject` as described under `runTest()`.

Return Value

`WebObject`

Syntax

```
startTest()
```

Parameters

None

stopSession

Stops the session, and waits for it to enter the *Stopped* state.

Return Value

None

Syntax

```
stopSession()
```

Parameters

None

stopTest

Stops the current running test.

Return Value

None

Syntax

```
stopTest()
```

Parameters

None

waitTestStopped

Waits for the current test to stop (when the test was started with **startTest**) and then checks for any error notifications. If it finds any error notifications, it throws a `WebException`.

Return Value

`WebException` if errors found.

Syntax

```
waitTestStopped()
```

Parameters

None

Statistic Class

Describes a statistic from the test.

Members

<code>session</code>	The current IxChariot session
<code>values</code>	The list representing values for the statistic over time, containing elements of the <code>StatisticValue</code> type

Functions

<code>add_value (value)</code>	Takes a <code>StatisticValue</code> as parameter, appends it to the list of values.
------------------------------------	---

StatisticValue Class

Describes a value for a statistic at a moment in time.

timestamp	The moment in the test when the value was recorded (in milliseconds)
value	The actual value recorded

WebObjects

Many APIs served by a ReSTful server return (and accept) objects as either an XML-or JSON-formatted text. The IxChariot server uses JSON. To make it easier to work with JSON, the `ixia.webapi` module includes a Python `WebObject` class that wraps the JSON text and allows for a simple object-like notation that is much simpler to type and manipulate than raw JSON strings.

For example, JSON objects are typically stored as a series of nested dictionaries and lists. A list of cars and their owners' names could be represented by the following dictionary:

```
carList = [{"model": "Ford", "year":2008, "priorOwners":[{"name": "Bill"}, {"name": "Mary"}]},  
{"model": "Toyota", "year":2010, "priorOwners":[{"name": "Ida"}, {"name": "Frank"}]}
```

When a car is sold, a new prior owner needs to be added, so the way to do this unassisted is:

```
carList[1]["priorOwners"].append({"name": "Ionut"})
```

This is a simple example, but the properties could hold other lists and dictionaries nested to an arbitrary depth. This quickly becomes unreadable. With a `WebObject`, the syntax becomes much easier to script:

```
carList[0].priorOwners.append(name="Ionut")
```

For more examples of manipulating web objects, review the sample scripts. Note that the properties are created dynamically to match the server response, so they are not documented here (it is specific to the web service and the WebAPI library has no service-specific code).